EDI0001 EDI Common Maintenance

Aptean Ltd
Copyright © 2011-2026.

Contents

1 EDI0001 EDI Common Maintenance.....1

1 EDI0001 EDI Common Maintenance

EDI common is used to dictate for what company/warehouse/owner the EDI flows are for.



Field Name	Description	Options	Generic Value
*Company Code **	Company code the user is setting up the EDI for	Must have been created in company maintenance	Defined by the client
*Warehouse ID **	The warehouse code the user is setting up the EDI for	Must have been created in warehouse maintenance	Defined by the client
*Message Type **	The message type of the EDI flow you are setting up	Defined by the hard coding of each EDI message - available message types listed below	See below
*Key 1 **	If the database is to have multiple owners under one warehouse/company combination the owner code for each message will need to be set up here	Owner code of the owner otherwise ?+? if only one owner per warehouse using EDI. **Advisable to always define the owner code.**	Defined by the client
*Key 2 **	If the database is to have multiple owners under one warehouse/company combination the owner sub code for each message will need to be set up here	Owner sub code otherwise ?+? if only one owner per warehouse using EDI.	Defined by the client
*Company Code **	Company code the user is setting up the EDI for	Must have been created in company maintenance	Defined by the client
*Warehouse Id **	The warehouse code the user is setting up the EDI for	Must have been created in warehouse maintenance	Defined by the client
*Department **	The department code set up against the company	Must have been created in departments maintenance	Defined by the client
*Ledger Code **	Determines which area of the system the message relates to	PL1 or SL1	See below
*Branch Code **	The branch code set up against the company (not required)	Must have been set up in branch code maintenance or set to '+'	+
*Owner Code **	The owner code and sub code the message is being set up for	Must have been created in owner maintenance	Defined by the client
*Stockist Code **(same as owner code)*	The owner code and sub code the message is being set up for	Must have been created in owner maintenance	Defined by the client

Ready for What's Next, Now™

Field Name	Description	Options	Generic Value
Base Currency **	The default currency code being used by the owner	Must have been created in currency maintenance	Defined by the client

Ready for **What's Next, Now**™