



Important note: When you edit this page, you agree to release your contribution into the **public domain**. If you don't want this or can't do this because of license restrictions, please don't edit. This page is one of the Public Domain Help Pages, which can be freely copied into fresh wiki installations and/or distributed with MediaWiki software; see [Help:Contents](#) for an overview of all pages.



This template is to be transcluded in **public domain** help pages.

This template will transclude the central en categories template, if the template exists. Include this template in any language subpages, to unify the page's categories across languages.

Example

- title: Help:Deleting a page --> transclude {{Help:Deleting a page/categories}}
- title: Help:Deleting a page/th --> transclude {{Help:Deleting a page/categories}}
- title: Help:Deleting a page/subpage --> transclude {{Help:Deleting a page/subpage/categories}}
- title: Help:Deleting a page/subpage/th --> transclude {{Help:Deleting a page/subpage/categories}}

Contents

- 1 Template:Category.....1**
 - 1.1 Example.....1
- 2 Category.....2**
 - 2.1 Example.....2
- 3 Template:If en.....3**
 - 3.1 Example.....3
- 4 If en.....4**
 - 4.1 Example.....4

1 Template:Category

See [talk page](#) for some logics behind this implementation.

Do not transclude this in PD help pages (Help namespace), since it seem to break the PD help guidelines, in that, this template name is too generic to be used in a fresh wiki installation. For PD help pages, use [Template:Help/Category](#) instead.

1.1 Example

See [Template:Help/Category#Example](#)

[[Category:{{{1}}}]/Category|Category]]



2 Category



Important note: When you edit this page, you agree to release your contribution into the **public domain**. If you don't want this or can't do this because of license restrictions, please don't edit. This page is one of the Public Domain Help Pages, which can be freely copied into fresh wiki installations and/or distributed with MediaWiki software; see [Help:Contents](#) for an overview of all pages.



This template is to be transcluded in **public domain** help pages to categorize those pages.

2.1 Example

```
{{Help/Category|MediaWiki Introduction|lang=zh}}
```

```
{{Help/Category|MediaWiki Introduction}}
```

Default value of `{{{lang}}}` will be `{{SUBPAGENAME}}` (which will be "fr", "ja", "th", for, "Page/fr", "Page/ja", "Page/th", respectively).

If you want to specify the sort key, you may instead use the form `[[Category:Cat name{{{Lang subpage}}}|sort key]]`. This template is equivalent to `[[Category:Cat name{{{Lang subpage}}}{{{En pagename}}}]]`, but it compute `{{{If en|...}}}` two times, while this template compute `{{{If en|...}}}` only once.

```
[[Category:{{{1}}}/Category |Help]]
```



3 Template:If en

Do not transclude this in PD help pages (Help namespace), since it seem to break the PD help guidelines, in that, this template name is not suitable to be included in a fresh wiki installation. For PD help pages, use [Template:Help/If en](#) instead.

3.1 Example

See [Template:Help/If en#Example](#)



4 If en



Important note: When you edit this page, you agree to release your contribution into the [public domain](#). If you don't want this or can't do this because of license restrictions, please don't edit. This page is one of the Public Domain Help Pages, which can be freely copied into fresh wiki installations and/or distributed with MediaWiki software; see [Help:Contents](#) for an overview of all pages.



This template is to be transcluded in **public domain** help pages.

4.1 Example

```
{{Help/If en|This is en base page|This is non-en subpage}}
```

- title: Help:Deleting a page, Help:Deleting a page/subpage
 - ◆ result: This is en base page
- title: Help:Deleting a page/th, Help:Deleting a page/Th, Help:Deleting a page/tH, Help:Deleting a page/TH
 - ◆ result: This is non-en subpage

