

Shipment Pallets

Aptean Ltd
Copyright © 2011-2026.

Contents

1 Shipment Pallets.....	1
1.1 Shipment Pallet Label Production.....	1


1 Shipment Pallets

Shipment Pallets are used in combination with or stand-alone from Packing and/or WCS functionality.

1.1 Shipment Pallet Label Production


Setup: In order to use the shipment pallet despatch functionality, a shipment label must first be produced. These labels use the last number type ?SHPP? in warehouse document numbering to determine the range to be incremented by 1. These labels are then put onto the despatch pallet and used to scan packs onto in order to despatch packs rather than orders.

1.1.1 Warehouse Document Numbering (WHS9020)



Ensure a Type value of SHPP has been entered.


1.1.1.1 Default Printer Maintenance (WHS0002)



Ensure a Default Printer value has been set up for all relevant users - see [Default Printers Maintenance \(WHS0002\)](#)

1.1.1.2 Shipment Label Print (WHS1941)

This screen allows you to print shipment pallet labels.




To produce the labels, enter the number of labels required followed by the start number.

Field Name	Description	Options
<i>Number of Pallet Labels</i>	The number of shipment pallet labels to be produced	0 - 999
<i>Shipment Pallet Id</i>	The specific shipment pallet id a label is to be reproduced for	Must be within the SHPP last number range (i.e. already had a label produced for it)
Buttons	Description	
Create	Updates the last number in warehouse document numbering and generates the labels	
Reprint	Reprints the selected number of labels or the label of the specific shipment pallet id selected	

1.1.2 Shipment Pallet Maintenance (WHS1942)

This screen allows you to maintain shipment pallets created from packing.






Field Name	Description	Options
Search By	Determines how the selection of packages will be made. The next field will display the shipment pallet number related to the selection criteria	Pack List No Order Number Package Id Shipment Pallet
Pack List No	Displays the pack list no assigned to the shipment pallet	Display only
Package Ref	Displays the pack ref of the order assigned to the shipment pallet	Display only
Pack Status	Displays the pack status for the pack list	Display only
Shipment Pallet	The shipment pallet number the package is assigned to	Display only
Pallet Location	The default shipment pallet location the package has been stored in prior to despatch	Must have been created in location codes maintenance
Interfaced	Displays the interface status of the package as to whether the carrier interface has been populated (client specific)	Y or blank
Order Number	The order number relating to the package id	Display only
Order Status	The status of the order	Display only
Invoice	Determines whether a commercial invoice has been received for the order (client specific)	Y or blank
Priority	The order priority of the package - note, dependant on the settings for the sharing of order priorities, some order priorities cannot be mixed on a shipment pallet	Display only
Carrier	The carrier code of the order associated with the package id	Display only
Buttons	Description	Options
Add Package	Enables the user to add specific packages to the selected shipment pallet	A popup box will appear prompting for pack ref - LOV available
Move Package	Allows the user to move selected packages onto other existing shipment pallets	-
Move Pallet	Moves all packages for this shipment pallet onto another existing shipment pallet	-



Buttons	Description	Options
Close Pallet	Closes the shipment pallet ready for despatch	If using commercial invoice, the pallet cannot be closed until all packs for the pallet have received a commercial invoice
Despatch Pallet	Despatches the pallet and sets all related orders to status 9	No despatch documentation is produced

1.1.2.1 Shipment Pallet Details Tab (WHS1942)



Field Name	Description	Options
Order Num	The order number of the selected pack ref	Display only
Line No	The order detail line no for the package	Display only
Rotation No	The system rotation (batch) for this package	Display only
Pallet Id	The system pallet id for this package	Display only
Haz	Displays a flag to determine whether the product on the package is hazardous or not	Y or N
Packed Cases	The quantity of cases for the pack ref	Display only
Packed Units	The quantity of units for the pack ref	Display only
Stockist Code/Sub Code	The owner code and sub code of the order	Display only
Stock Code	The product code of the goods packed on this pack ref	Display only

