



Aptean

Maintenance - Resources Guide

Calidus TMS - 12.48

31st July 2025 - 3.01
Reference: Maintenance

Contents

1 Resources Maintenance.....	1
1.1 Carriers.....	1
1.2 Carrier Groups.....	5
1.3 Carrier Lanes.....	5
1.4 Carrier Types.....	7
1.5 Carrier Service Level.....	8
1.6 Service Types.....	8
1.7 Fixed Charges.....	9
1.8 Trailer Types.....	9
1.9 Trailer Group.....	12
1.10 Trailers.....	13
1.11 Drivers.....	15
1.12 Loc Prd Conv.....	21
1.13 Despatch Unit Types.....	22
1.14 Standardised DU's.....	24
1.15 RPEs.....	24
1.16 RPE Cust.....	24
1.17 Load Rates.....	25
1.18 Despatch Units.....	27
1.19 Tractors.....	27
1.20 Vessels.....	29
1.21 Resource Availability.....	30
1.22 Carrier Routing.....	30
1.23 Carrier Routing UKMail.....	30
1.24 Carrier Formats.....	31
1.25 Carrier Tracking.....	31
1.26 Carrier Config.....	32
1.27 Vehicles.....	32
1.28 Carrier Hazard Qty.....	35
1.29 Carrier Formats Mapping.....	35

1 Resources Maintenance

The Resources module encompasses the maintenance of the Resources used throughout the C-TMS system. Resources define the various core entities used in the transport system to enable trips to be made. These are entities such as Carriers, Trailers, Despatch Unit Types and Drivers. Resources data is used by many of the key functions in C-TMS including [Trip Manipulation](#), [Generate TI's](#) and [Bookings](#).

The data can be viewed, created, edited and maintained through the accompanying Resource Maintenance form.

The screenshot shows the 'Edit Carrier' screen of the Resource Maintenance software. The main form is titled 'Edit Carrier' and contains the following fields:

- Carrier ID:** AD TRANSPORT
- Carrier Name:** A & D TRANSPORT
- Alternate Name:** [empty]
- Carrier Type:** MTS CARRIER R/
- Current Haulage Units:** [empty]
- Group Name:** Hauliers
- Display Type:** Freetext
- Tracking:** [empty]
- Permit Debrief:** [checkbox]
- Inactive:** [checkbox]
- External Drivers:** [checkbox]
- TMS Ref:** [empty]
- Address:** [text area]
- Town:** [text area]
- County:** [text area]
- Country:** [text area]
- Postal Code:** [text area]
- Country (ISO Code):** [dropdown]
- Contact:** [text area]
- Phone:** 123456
- Fax:** [text area]
- Email:** [text area]
- Cost Centre:** [dropdown]
- Trips per day:** [dropdown]
- Reporting Carrier:** [dropdown]
- Multiple Tariff:** [checkbox]
- Allow Palletisation:** [checkbox]
- EPOD Enabled:** [checkbox]
- Auto Debrief Col:** N
- Send to ePOD Col:** Y
- Single Box tracking:** [checkbox]
- Transport Mode:** [dropdown]
- 3rd Party Labels Required:** [checkbox]
- Air Waybill/Consignment Required:** [checkbox]
- Default Resource:** [checkbox]
- Auto Debrief Del:** N
- Send to ePOD Del:** Y
- OTM Enabled:** [checkbox]
- Van Fleet:** [checkbox]
- Flexipod:** [checkbox]
- LogNext Enabled:** [checkbox]
- Hub Location:** [text area]
- Enforce Start at Hub:** [checkbox]
- Barcode Type:** [dropdown]
- Country of Registration:** GB
- Great Britain & GST Number:** [text area]
- HQ Location:** [text area]
- Enforce End at Hub:** [checkbox]
- Export File type:** [dropdown]
- Enforce Start at Del:** [checkbox]
- Trip Threshold Hours:** [text area]
- Stopover Threshold (Work Hrs):** [text area]
- Driver Break Threshold (Hrs.):** [text area]
- Standard Shift Hours:** [text area]
- Stopover Threshold (Drive Hrs):** [text area]
- Driver Break Duration (Mins.):** [text area]
- Overtime Factor:** [text area]
- Stopover Duration (Mins.):** [text area]
- Max DU per Shipment:** [text area]
- Work Break Threshold (Hrs.):** [text area]
- Max Shift Hours:** [text area]
- Payment Deadline:** [text area]
- Work Break Duration (Mins.):** [text area]
- Standard Factor:** [text area]
- MPG:** [text area]
- MU ID:** [text area]
- SC Type:** [dropdown]

At the bottom of the form are 'Look Up...', 'Save', and 'Cancel' buttons.

1.1 Carriers

The Carrier tab of the Resources Maintenance screen allows carrier information to be configured.



Resource Maintenance																				
RESOURCES v2.213 C-TMS v11.39																				
Carriers Carrier Groups Carrier Lanes Carrier Types Carrier Service Level Service Types Fixed Charges Trailer Types Trailer Group Trailers Drivers Loc Prd Conv																				
<input type="radio"/> Active	<input type="radio"/> Inactive	<input type="radio"/> All	Carrier ID	Name	Group	Carrier Type	Haul Unit	Hub Loc	Start End Hub	BC Type	TMS Ref	HQ Loc	Exp Type	GST No	MS	TT	SS	SF	OTF	Alt Mul Car Tar I/A E/D
AD TRANSP	A & D TRANSP	Hauliers	MTS CARR																	
ADAMS	ADAMS TRANSP	Hauliers	Fleet													13	8	9	1.00	0.50
AHC	AHC II	Hauliers	MTS CARRI																	
AIRAU	Air Australia	Hauliers	Haulier																	
AIRROA	Air Road Express	ROADFRI	LINEHAUL	1																
AJ BRUNT	AJ BRUNT	Hauliers	MTS CARRI																	
AKUBRA LGS	Akubra Logistics	Hauliers	MTS CARRI																	
AL-ARABIA	AL-ARABIA Transp	EXEL-SA	PARCEL																	
AL-JABRI	AL-JABRI Transpo	EXEL-SA	PARCEL																	
AL-LE TRAN	AL-LE Transport	Hauliers	MTS CARRI																	
AL-MARRI	AL-MARRI Transp	EXEL-SA	PARCEL																	
ALAN R JONE	Alan R Jones & Sons	Hauliers	MTS CARRI																	
ALAN SMITH	Alan Smith	Hauliers	MTS CARRI																	
ALB	St Albans	POLAR S	Fleet					ALB	✓										9	
ALBERTI	ALBERTI	Hauliers	Haulier																	
ALLICOOK	ALLINGHAM TRAN	Hauliers	MTS CARRI																	
ALLINSONS	Allinsons & Sons	Hauliers	Haulier																	
AM	AM Transport	Hauliers	MTS CARRI																	
AMESKO	PPH Amesko Sp. J	Hauliers	Haulier																9150003	
AMSCO	Amsco Logistics	Hauliers	Haulier																	
Fuel Surchar... New Carrier Contacts Edit Delete																				
Apply Close																				

Carriers can be connected to carrier groups and can be of a certain type. For example, FLEET type is part of the business or client using C-TMS whereas HAULIER may be deemed to be 3rd parties.

One use of the carrier records is to record typical fleet routes or groups so that planning personnel in other areas of the system, such as when using Trip Manipulation can easily identify them.

You can click **New Carrier** to create a new carrier:

Resource Maintenance																	
RESOURCES v2.213 C-TMS v11.39																	
Carriers Carrier Groups Carrier Lanes Carrier Types Carrier Service Level Service Types Fixed Charges Trailer Types Trailer Group Trailers Drivers Loc Prd Conv																	
Edit Carrier																	
Carrier ID AD TRANSPORT Carrier Name A & D TRANSPORT Alternate Name <input type="text"/> Carrier Type MTS CARRIER R/																	
Current Haulage Units <input type="text"/> Group Name Hauliers Display Type Freetext Tracking <input type="text"/> Permit Debrief <input type="checkbox"/> Inactive <input type="checkbox"/> External Drivers <input type="checkbox"/> TMS Ref <input type="text"/>																	
Address <input type="text"/> Multiple Tariff <input type="checkbox"/> 3rd Party Labels Required <input type="checkbox"/> Current Haulage Units <input type="text"/> Group Name Hauliers Display Type Freetext Tracking <input type="text"/> Permit Debrief <input type="checkbox"/> Inactive <input type="checkbox"/> External Drivers <input type="checkbox"/> TMS Ref <input type="text"/>																	
Town <input type="text"/> Allow Palletisation <input type="checkbox"/> Air Waybill/Consignment Required <input type="checkbox"/> County <input type="text"/> EPOD Enabled <input type="checkbox"/> Default Resource <input type="checkbox"/> Country <input type="text"/> Auto Debrief Col <input type="checkbox"/> N <input type="checkbox"/> Send to ePOD Col <input type="checkbox"/> Y <input type="checkbox"/> Auto Debrief Del <input type="checkbox"/> N <input type="checkbox"/> Send to ePOD Del <input type="checkbox"/> Y <input type="checkbox"/> OTM Enabled <input type="checkbox"/> OTM Enabled <input type="checkbox"/> Postal Code <input type="text"/> Single Box tracking <input type="checkbox"/> OTM Enabled <input type="checkbox"/> Van Fleet <input type="checkbox"/> Flexipod <input type="checkbox"/> Contact <input type="text"/> Phone <input type="text"/> 123456 <input type="text"/> Trips per day <input type="text"/> Reporting Carrier <input type="text"/> LogiNext Enabled <input type="checkbox"/>																	
Hub Location <input type="text"/> Enforce Start at Hub <input type="checkbox"/> Barcode Type <input type="text"/> Country of Registration GB Great Britain & HQ Location <input type="text"/> Enforce End at Hub <input type="checkbox"/> Export File type <input type="text"/> GST Number <input type="text"/> Enforce Start at Del <input type="checkbox"/> Cost Centre <input type="text"/> Max DU per Shipment <input type="checkbox"/> MU ID <input type="text"/> Standard Factor <input type="text"/> Payment Deadline <input type="text"/> MU ID <input type="text"/> SC Type <input type="text"/> MPG <input type="checkbox"/>																	
Trip Threshold Hours <input type="text"/> Stopover Threshold (Work Hrs) <input type="text"/> Driver Break Threshold (Hrs) <input type="text"/> Standard Shift Hours <input type="text"/> Stopover Threshold (Drive Hrs) <input type="text"/> Driver Break Duration (Mins) <input type="text"/> Overtime Factor <input type="text"/> Stopover Duration (Mins) <input type="text"/> Max DU per Shipment <input type="checkbox"/> Work Break Threshold (Hrs.) <input type="text"/> Standard Factor <input type="text"/> Payment Deadline <input type="text"/> Work Break Duration (Mins.) <input type="text"/> MU ID <input type="text"/> SC Type <input type="text"/> MPG <input type="checkbox"/> Look Up... Save Cancel																	

A variety of attributes are configured here for each Carrier record such as *V.A.T. number*, *hub location*, *maximum shift time*, *fixed costs* and *head quarters (HQ Location)*.

Save will save the changes, note a message at the bottom of the form will confirm the save.

Ready for **What's Next, Now™**



You can continue entering your next haulier or click **Cancel** to close the form.

The haulier is now visible in the *Carrier* tab.

Additional fields include:

- **Display Type** - Note that the *Display Type* can be set to either "Poplist" or "Freetext", the latter will allow free text entry of data into the trips allocated to this carrier (driver, vehicle etc) and the former will force you to select data from predetermined lists which we will see later in this section. This is normally set to "Poplist" for internal fleet carriers, as the assets should be fixed and can therefore be pre-populated.
- **Hub Location/Enforce Start at Hub/Enforce End at Hub** - Fleet resources should be set up with a *Hub Location* and the *Enforce Start at Hub* and *Enforce End at Hub* boxes ticked to enable them to operate correctly. This will ensure that all trips allocated to these carriers will start and end at this location as opposed to hauliers who will generally be utilized from location to location rather than round trips.
- Additionally the *Trip Threshold Hours*, *Standard Shift Hours*, *Overtime Factor*, *Max Shift Hours* and *Standard Factor* should be populated with default fleet data.
- **Current Haulage units** - This is a numeric field that has no validation behind it but give the user an indication as to how many Tractor Units the Carrier has control over. It assists mainly when tendering out large jobs to 3rd party Hauliers so that they can see if the Haulier is big enough to take the job on.
- **Permit Debrief** - Checking this box gives Permission to the Carrier to allow them to debrief their own Trips via the [Carrier Trip Management](#) Screen.
- **Transport Mode** - indicates the type of carrier (ROAD or AIR).
- **Tracking** - This drop down list triggers the interface with a Smartphone application that allows real time debriefing. It can be set against a Carrier or an individual Driver. There are also a number of system parameters shown in the table below that need to be enabled for the Application.
- **EPOD enabled** - indicates if trips the carrier is assigned to are sent to Aptean POD - Calidus Edition (CALIDUS ePOD) for execution and automatic debrief.
- **Flexipod** - indicates if the carrier is using the Aptean POD (APOD or formerly FleXipod) system for execution and automatic debrief. This applies only if the system is configured to use this flag in system parameters.
- **LogiNext Enabled** - indicates if the carrier is using the LogiNext 4PL system to manage a 3rd party carrier trip assignment and automatic debrief. See [Using the LogiNext Carrier Interface](#) for more information on this process.

You can edit an existing carrier by selecting it from the table and clicking the **Edit** button. This will show the same screen as adding a new carrier, but with all of the information populated.

You can delete an existing carrier (if it has not been used) by clicking the **Delete** button.

You can also access and edit the following information about the carrier through the buttons provided:

- **Fuel Surcharges**.
- **Contacts**.

1.1.1 Fuel Surcharges

Fuel surcharges are used when generating trip costs for trips executed by that carrier.



The fuel surcharge is applied on trips that were executed (started) on or following the *Effective Date* supplied.

You can add a new surcharge by clicking in an empty row and entering the information (*Effective Date*, *Fuel Surcharge*). You can edit a row by clicking on that row. You can **Save** your changes with the button provided, or discard any changes with the **Close** button. You can also delete an existing contact using the **Delete Record** button provided.

1.1.2 Contacts

This information may be used for reference if sending documents to the carrier.

You can add a new contact by clicking in an empty row and entering the information (*Surname*, *Forename*, *Title*, *Phone*, *Email*). You can edit a row by clicking on that row. You can **Save** or **Cancel** your changes with the buttons provided. You can also **Delete** an existing contact using the button provided.

You can add a new contact by clicking in an empty row and entering the information (*Surname*, *Forename*, *Title*, *Phone*, *Email*). You can edit a row by clicking on that row. You can **Save** or **Cancel** your changes with the buttons provided. You can also **Delete** an existing contact using the button provided.



1.1.3 Imports

Carrier records can also be created and updated by synchronisation between the external applications and C-TMS, especially where the client offers the trips for tender to third-party hauliers, and, where new hauliers may bid for business.

Carriers may be created via imports:

- CARRIER

1.2 Carrier Groups

Carrier Groups are used to define reporting priorities.

To create a new group, click on **New** to open the form. Enter the "Name" and "Report Seq" which controls the priority and then click **Save** to return to the main form. You can click on **Cancel** to cancel your entry.

You can also enter an EPOD Site - this is the general grouping of carriers within your Calidus EPOD system, if you have it and if it is configured for carrier-level sites.

The **Edit** button can be used to edit the groups and therefore change the reporting sequence. Generally two "Carrier Groups" require mandatory set up: a "Fleet" and "Haulier". Old Groups can be deleted using the **Delete** button provided that there are no associated records.

1.3 Carrier Lanes

The Carrier Lanes tab of the Resources Maintenance screen allows you to configure different carrier lanes. This is bespoke to carrier lanes functionality for third-party carriers.



You can search by the following criteria:

- Lane ID
- Lane Group
- Region - a planning group lookup is provided.
- Carrier
- Collect
- Deliver
- Procured
- Lane Type
- Trailer Type - a trailer type lookup is provided.
- Historic
- Inactive

You can refresh the data shows using the **Refresh** button, and clear the criteria using the **Clear Search Criteria** button.

You can view the following information:

- Lane ID
- Region - a planning group lookup is provided.
- Lane Group
- Country
- Carrier
- Country
- Collect
- Country
- Type - A drop-down list, one of Postcode, Postal Region, Planning Region, Distance Greater, Distance Less or Anywhere.
- Deliver
- Procured
- Lane Type
- Action - A drop-down list, one of Manual Planning, Create Trip or Brief Trip.
- Currency
- Cost
- Trips
- Rate Ref
- Tariff
- Start Date
- End Date




- **Trailer Type** - a trailer type lookup is provided.
- **Cost Centre** - a cost centre lookup is provided.
- **Inactive**

Actions are available through the following buttons:

- **New** - create a new record, entering all of the above data.
- **Delete** - delete the selected record.
- **Copy Record** - copy the selected record
- **Cancel** - discard any changes.
- **Save** - save changes
- **Group**
- **Update Rates**
- **Audit**

1.4 Carrier Types

Configuration of the different Carrier Types in the system is possible in the Carrier Types tab of the Resources Maintenance screen. This information can be typically used to distinguish between a client's own fleet and external carriers. Areas such as Accounting and Profit & Loss to determine where to assign revenue and costs can use this information.



Carrier Type ID	Order Cost	Trip Cost	MPG
MTS CARRIER RATE	CONTRACT	CONTRACT	
TDL_Fleet	CONTRACT	CONTRACT	
PARCEL			4
DHL Depot	CONTRACT	CONTRACT	
3PL			
NHS-OWN			
Fleet			4
Customer			
Haulier			
Non Charging			
Handoff			
Parcel			
Open Tier1	CONTRACT	CONTRACT	
3 - Regular	CONTRACT	CONTRACT	
1 - Tier 1 Preferred	CONTRACT	CONTRACT	
2 - Tier 2 Preferred	CONTRACT	CONTRACT	
4 - Backup	CONTRACT	CONTRACT	
Openfield Forwarder	CONTRACT	CONTRACT	2.63
Owner Driver	CONTRACT	CONTRACT	
DMM-OWN			

The carrier type is linked to the carrier and also the various costing methods associated with freight payment. To set up a new type click **New**.

Enter the "Carrier Type" and then the "Trip Cost Method" and "Order Cost Method" - these are optional.

There are four types of cost method that can be applied to the carrier, these are:


- "MANUAL" whereby the cost can be allocated to the trip manually,
- "EXTERNAL" whereby the trip cost will be allocated from an external source like MTM,
- "CONTRACT" whereby the trip cost will be calculated within CT<S via contracts and tariffs and
- "EXT_CONTRACT" which looks for an external value and if one is not found it uses the "CONTRACT" method.

An MPG value can be recorded as a default MPG per vehicle type which can be used in CO2 emissions calculations per trip when lower level vehicle based MPGs are not available.



1.5 Carrier Service Level

The Carrier Service Level tab of the Resources Maintenance screen allows you to specify a cross-reference of carrier service levels.




You can enter:

- Carrier ID - a lookup is provided.
- Product Type - a drop-down list is provided.
- Service Level - a lookup is provided.
- Carrier Service Level - the carrier service level to use.
- EDI Carrier Service Level - the carrier service level to use in EDI messages.

1.6 Service Types


The different services that carriers may supply can be maintained here. These can be linked to the delivery type of orders to enable calculation of the cost of deliveries for particular order types.





1.7 Fixed Charges


This section allows set costs to be configured for groups of carriers, such as own fleet for a certain depot.



1.8 Trailer Types

This section allows configuration of different trailer types used in the system. Various parameters for each trailer are set here and affect how a trailer is chosen in processes such as [Generate Transport Instructions](#) and [Trip Manipulation](#).






The screen shows:

- Trailer Type - a unique trailer type that can be applied to trailers.
- Description - a description of the trailer type.
- Volume - the volume of the trailer.
- Max KG - the maximum weight that the trailer can safely hold. **Note:** that this can limit the orders automatically planned onto vehicles or trailers of this type for fixed routes, and will produce a warning if exceeded when manually planning orders onto a vehicle or trailer of this type.
- Max RPE - constrain how much that type can hold, based on the combined RPE of the DU Types loaded on the vehicle or trailer of this type. **Note:** that this can limit the orders automatically planned onto vehicles or trailers of this type for fixed routes, and will produce a warning if exceeded when manually planning orders onto a vehicle or trailer of this type.
- Length - the length of the trailer. Note that Location restrictions can prevent the use of vehicles or trailers of this type based on the length of the trailer.
- DT Mod (Drive Time Modifier) - For normal trailers, this should be set to 1, This can be used to factor speeds for trailers or vehicles such as vans and make them faster than articulated Lorries, or to reduce the time taken for large or extra-wide trailers. For example, a vehicle with the "Drive Time Modifier" set to "0.5" would be twice as fast as one with a value of "1.0", which would be twice as fast as a trailer set with a value of 2. **Warning:** Trailer and vehicles set to a trailer type with a Drive Time Modifier of 0 will result in a time between stops on trips of 0. This directly affects time and distance calculations and makes trips require manual intervention on stops and require the stops to be fixed.

This section also allows configuration of the types of compartment present in a trailer of this type, how much each compartment can hold and how the different temperature types can be combined together.

To set up a new Trailer Type click **New**.






Note that the "Drive Time Modifier" defaults to a value of "1.00" this can be used to factor speeds for vehicles such as vans and make them faster than articulated Lorries. For example, a vehicle with the "Drive Time Modifier" set to "0.5" would be twice as fast as one with a value of "1.0".

Click **Save** to save your changes and return to the main form, or **Close** to close and return without saving changes.

The trailer also has to have the compartments defined. This is shown on the right hand section of the screen, which enables you to allocate temperature compatibilities to the trailer types dependent on the site configuration and utilization. For example it may be possible to run with Chilled products on the headboard of the trailer and Ambient goods on the rear but not the other way round, this can be specified per trailer type. N.B. this section must be completed in order for trailers to be allocated to trips. Click **New**:



When setting up a new trailer type, you have to specify the length, volume and maximum RPE (Roll Pallet Equivalent) capabilities for that trailer which will be used when allocating the trailer to trips. The "Trailer Type" should give an abbreviated but concise description of the trailer as this will appear in "Trip Manipulation" and on reports, and the "Description" should be more detailed so that it is evident to transport departments exactly which trailer is required for the trip.

In most cases it will be the RPE value that governs the capacity of the trailer and once this has been set a trailer will not automatically allocate to a trip if its RPE capacity has been exceeded. There is also further validation with regard to trip creation and trailer validation, for example the smallest feasible trailer will be allocated to a trip in the first instance and if the largest possible trailer type is allocated and the capacity exceeded the trailer type will be maintained.

The trailer type allocated to the trip governs the "Trailer ID" which can be allocated if a carrier set to "Poplist" is being used and the "Refrigerated" and "Cost" boxes will restrict the usage of the trailers as it will use others first unless otherwise constrained (via restrictions set up by location). Constraints are generally defined by length which is why this is an important field to populate.

Temperature types represent certain types of goods that require storage at a certain temperature range. The temperature combination entries determine how the temperature types can be combined and in which compartments on a trailer they should be stored.

Click **Save** to save your changes and return to the main form, or **Close** to close and return without saving changes.

When setting up a new trailer type you have to specify the length, volume and maximum RPE (Regular Pallet Equivalent) capabilities for that trailer which will be used when allocating the trailer to trips. The Trailer Type should give an abbreviated but concise description of the trailer as this will appear in Trip Manipulation and on reports, and the Description should be more detailed so that it is evident to transport departments exactly which trailer is required for the trip.


In most cases it will be the RPE value that governs the capacity of the trailer and once this has been set a trailer will not automatically allocate to a trip if its RPE capacity has been exceeded. There is also further validation with regard to trip creation and trailer validation, for example the smallest feasible trailer will be allocated to a trip in the first instance and if the largest possible trailer type is allocated and the capacity exceeded the trailer type will be maintained.

The trailer type allocated to the trip governs the Trailer ID which can be allocated if a carrier set to "Poplist" is being used and the "Refrigerated" and "Cost" boxes will restrict the usage of the trailers as it will use others first unless otherwise constrained (via restrictions set up by location). Constraints are generally defined by length which is why this is an important field to populate.

1.9 Trailer Group

You can specify trailer groups here. These are used when specifying trailer types.






You can enter the group ID and name here.

1.10 Trailers

This allows configuration of instances of trailers. This can be used for tracking trailers throughout the system. This tab also allows Trailers to be linked to a particular Carrier Group to control who is able to user the Trailer.



To enter a new trailer click **New**:



The screenshot shows the 'Insert Trailer' screen within the RE SOURCE software. The main area contains fields for 'Trailer Id', 'Trailer Type', 'Tracking System', and 'Cost Centre Name'. Below these are three dropdown lists: 'Carrier Groups', 'Tractors', and 'Allocation to Resources'. The 'Allocation to Resources' section displays a table with columns for 'Carrier Group' and 'Inactive'. The row for 'Polar Speed' is highlighted with a yellow background and has a checked 'Inactive' box. Buttons for 'Look Up...', 'Next', 'Save', 'Cancel', 'New', 'Edit', 'Apply', and 'Close' are visible at the bottom.

The Trailer ID can be entered and a Trailer type selected. You can also identify the tracking system used for this particular trailer.

Click **Save** and the system will confirm the trailer has been saved - if you haven't entered a carrier group, the screen will tell you it needs to be allocated to a trailer group. Click **OK**. You can then enter a subsequent trailer or click **Cancel** to return to the main form.

The Trailer ID can be linked to a particular Carrier Group for ownership purposes. This controls the visibility of trailer ID selection based on the user's access parameters.

You can do this in this popup screen. Click in the Carrier Groups table and hit CTRL-L to see a lookup of all carrier groups. Select one and click **OK** - the carrier group will be assigned.

Click **New** in "Allocate to Resources" section to add to a Carrier Group (or **Edit** the Trailer ID). Allocate a carrier group to the trailer as described above. This will normally be "Fleet" for own fleet or "Hauliers" for 3rd party carriers.

Click **Save**. The trailer is now allocated to a carrier group. The trailer will now be available to assign to a trip.

The Trailer ID can also be linked to one or more Tractor IDs - this will limit which Trailer IDs can be assigned to a trip where a Tractor ID is first applied. It denotes which trailer can be drawn by which tractor. It can also be used as a one-to-one link where a tractor/trailer represent a rigid vehicle. Click **New** in the "Tractors linked to Trailers" section (or **Edit** the Trailer ID).

If a trailer id is no longer required you are able to make it inactive.

Using the search buttons find the trailer you want to make inactive and click **Edit** from the Allocation to Resources box.

Click in the "Inactive" check box, so a tick appears to deactivate the whole trailer or mark the specific Tractor links or Carrier Group links as inactive "Y".

Click **Save**. The trailer id is now inactive.

You can also import trailers through **Imports**:

- **TRAILER**



1.11 Drivers

This allows a record to be kept of each driver in the system. Typically, this allows reports to show which drivers are assigned to which trips.

ID	Surname	Forename	Job Title	Contact No	EPOD User	Tracking	Exc	Inactive	Agency
1	Slawinski	Sebastian	BULK						
2	Lopes	Rui	DEBRIEFER						
3	Haynes	Mark	DEPOT MANA						
4	Meekings	David	DESPATCHER						
5	Shaw	Iewis	MULTI-DROP						
6	Bettoney	Edward	MULTI-DROP						
7	Gibson	Chris	MULTI-DROP						
8	Sandulache	Daniel	MULTI-DROP						
9	Bell	Christopher	MULTI-DROP						
10	Bull Hasley	Stephen	MULTI-DROP						
11	Stewart	Mark	MULTI-DROP						
12	Joof	Moses	MULTI-DROP						
13	Holecek	Pavel	TRUNK						
14	Chojnacki	Jaroslav	BULK						
15	Clair	Mark	DEBRIEFER						
16	Schofield	Wayne	DEPOT MANA						
17	Day	Steve	DESPATCHER						
18	Dawson	Peter	MULTI-DROP						
19	Bowett	Chris	MULTI-DROP						
20	Yorke	Steven	MULTI-DROP						

In much the same way as the "Trailers" tab enables specific trailer resources to be set up, the "Drivers" tab enables the actual drivers to be set up so that they can be allocated to trips with vehicles.

Isotrak's Manifest system, used by some client's transport personnel, allows drivers to be assigned to trips. Isotrak updates C-TMS with this information as trips are assigned to and accepted by drivers.

There are several actions available through buttons on the bottom of the screen:

- **Diary Exceptions** - see section below.
- **Show Shifts** - see section below.
- **Show Attributes** - see section below.
- **New** will allow a new activity to be entered for the current resource.
- **Edit** will allow editing of a record. When a resource is marked as unavailable, on holiday, absent or off the road if it has been allocated to any subsequent activity a message will be displayed warning the user they may need to take action to remove resources from trips etc.
- **Delete** will display a confirmation message and once confirmed will remove the record
- **Apply** allows you to save any changes you have made.
- **Close** will save any changes and return you to the main resource diary page.

1.11.1 Adding a New Driver

New drivers can be entered using the **New** button and existing drivers either edited or inactivated using the **Edit** button.

From the Drivers box click **New**:



The screenshot shows the 'Resource Maintenance' software interface. The main window is titled 'Resource Maintenance' and has a toolbar with icons for back, forward, search, and help. The top menu bar includes 'Carriers', 'Carrier Groups', 'Carrier Lanes', 'Carrier Types', 'Carrier Service Level', 'Service Types', 'Fixed Charges', 'Trailer Types', 'Trailer Group', 'Trailers', 'Drivers' (which is selected), and 'Loc Prd Conv'. The 'Drivers' tab is active, showing a list of drivers with columns for ID, Surname, Forename, Job Title, Contact No, EPOD User, Tracking, and checkboxes for 'Exc', 'Inactive', and 'Agency'. A 'Refresh' button is at the top right of the list. Below the list are buttons for 'Diary Exceptions', 'Show Shifts', 'Show Attributes', 'New', 'Edit', and 'Delete'. To the right of the list is a panel titled 'Allocation to Resources' with a table for 'Carrier Id' and 'Inactive' status. It shows entries for 'ANG' (checked) and 'LBZ' (unchecked). Buttons for 'New' and 'Edit' are at the bottom of this panel. At the bottom of the main window are 'Apply' and 'Close' buttons.

Enter the "Id" this is a free text field and would normally be the drivers payroll number, "Job Title" which is a system value and will generally be "DRIVER" enter D and return, "Forename" and "Surname" are both free text fields. A driver can be set to indicate that they have access to a Tom Tom or WEBFLEET device.


You can allocate to resources (carriers) here, as well as entering attributes for the driver - both of these processes are covered in sections below.

Click **Save** and the system will confirm the driver has been saved, but needs to be linked to a carrier. Click **OK**. You can then enter a subsequent driver or click **Cancel** to return to the main form.

1.11.2 Allocate to Resources

To allocate to resources, select the driver and from the Allocation to Resources section, click **New**. Allocate a carrier id to the driver. This will be the carrier id of the depot where the driver is based.





Click **Save**. The driver is now allocated to the carrier id. The driver will now be available to assign to trips using the chosen carrier.

Note that you can also specify the following here:

- Hub Location - a location where the driver is based, for example, another depot, home, etc. CTMS will use this location in preference to the carrier hub location when creating trips.
- Vehicle ID - where the driver has a default vehicle, you may specify this here. Note that this affects ONLY the CTL Call Logging screen, not core CTMS.

1.11.3 Making a Driver Inactive

If the driver id is no longer required you are able to make it inactive. This follows the same process as making a trailer id inactive.

Using the search buttons find the driver you want to make inactive and click **Edit** from the Allocation to Resources box.

Click in the "Inactive" check box, so a tick appears.

Click **Save**. The driver id is now inactive.

1.11.4 Driver Attributes

Additionally, more detailed driver attributes can be recorded. Pressing the Attributes button displays a popup window in which the specific attributes can be entered:



The screenshot shows the 'Person Attributes' screen. At the top, there is a header bar with the application name. Below it is a main content area divided into several sections:

- Driver:** Contains fields for Driver Id (1), Name (Sebastian Slawinski), and Address. It also includes fields for DOB and Employment Start, along with New, Edit, and Delete buttons.
- Qualifications:** A table with columns for Qualifications, Valid From, and Valid To. It includes New, Edit, and Delete buttons and a 'Close' button.
- Vehicle Types:** A table with columns for Vehicle Id and Description. It includes New, Edit, and Delete buttons and a 'Vehicle Type' header.

At the bottom of the main content area are buttons for New, Edit, Delete, Apply, and Close. To the right, there is a sidebar titled 'Resources' with a list of items and an 'Edit' button.

Each section of the screen has three buttons:

- **New** - See Below
- **Edit** - See Below
- **Delete** - A message will be displayed asking the user to confirm the deletion, once confirmation is received the current record will be removed from the database.

A **Close** button is included in the bottom of the screen, when pressed if there are any un-committed changes a message will be displayed to ask the user to Save or abandon the changes before the screen is closed.

1.11.4.1 New/Edit

The **New** or **Edit** buttons are pressed a popup window will be displayed to allow creation or updating of a record.

1.11.4.2 Driver Details

This is a dialog box for 'Person Attributes'. It contains the following fields:

- Driver Id: 22851318
- Name: Sajid Ali
- Address: 12 Smith Street
- Town/City: Manchester
- County: GB
- Postcode: M1 1AB
- Dob: 01/01/1980
- Start Date: 06/06/2000

At the bottom of the dialog are 'Save' and 'Cancel' buttons.



The address fields are free format text and the DOB and start date will be date values.

1.11.4.3 Qualifications

Person Id	22851318
Name	Sajid Ali
Qualification	Advanced Driver Course
Valid From	01/01/2014
Valid To	01/01/2015

Save Cancel

The Qualification field is free format text and the "Valid From" and "Valid To" are both Date fields.

1.11.4.4 Vehicle Types

Person Id	22851318
Name	Sajid Ali
Vehicle Type	A1

Save Cancel

The Vehicle type will be selected from a list of values from the Trailer Type master data.

In all cases two buttons are included

- **OK** - validate and commit changes then close the popup.
- **Cancel** - display a confirmation message if there are uncommitted changes, once confirmation is received changes will be rolled back and the popup window closed.


These driver attributes can also be directly accessed for view and edit from the main Drivers tab using the **Show Attributes** button at the bottom of the screen.

1.11.5 Diary Exceptions

The Diary Exception button displays a popup window showing the activity a current resource has been allocated to, along with any diary exceptions added for that driver, such as holidays, sickness, etc.

The data will be displayed in descending date and will be display only when first opened:





There are four buttons on the screen:

- **New** will allow a new activity to be entered for the current resource.
- **Edit** will allow editing of a record. When a resource is marked as unavailable, on holiday, absent or off the road if it has been allocated to any subsequent activity a message will be displayed warning the user they may need to take action to remove resources from trips etc.
- **Delete** will display a confirmation message and once confirmed will remove the record
- **Close** will save any changes and return you to the main resource diary page.

Note that the exceptions screen will be used to setup manual exceptions to the driver's shift availability, for example, the driver is unavailable for transport work while attending a training session.

To create a new record press the **New** button and enter the reason for the exception. Then enter the start and end date and time. The duration is calculated automatically.

Press the **Save** button to commit the record to the database. To delete a record press the **Delete** button.

 **Note:** Exceptions records created by planned trip activity related to the vehicle cannot be deleted.


Pressing the **Close** button will return you to the main screen.

1.11.6 View Shifts

You can view drivers shifts from here.

The **Show Shifts** button will display a new popup window to display the drivers shift patterns:





All data is display only.

The following actions are available from the buttons on the bottom of the screen:

- The **Close** button will return you to the main screen.
- The **Delete** button will display a confirmation message to confirm the delete. Once deletion is confirmed the record will be removed.

This data is related to the "Shift Patterns" data which is maintained in the "Business Data Maintenance" screen. This also provides functionality to generate shifts against the drivers. Further information can be found in the user guide covering the [Business Data Maintenance](#) screen.

1.11.7 Imports

Drivers (and associated reference data) may also be imported through [Imports](#):

- [DRIVERS](#)
- [DRIVER_SHIFT](#)
- [PERSON](#)

1.12 Loc Prd Conv

This allow you to enter product type conversion factors per location.



You can enter:

- Location ID - a lookup is provided.
- Product Type - a lookup is provided.
- Conversion Factor - a number to multiply.

1.13 Despatch Unit Types

This allows configuration of dispatch unit types.



Despatch Unit Types are the physical resources on which goods are despatched and delivered; e.g. pallets or roll cages. When setting up the DU Type the volume and maximum weight capacities need to be known and entered. The RPE value will be used when orders are being generated and if using Pallets rather than Roll Pallets (Cages) this value should be set to one so as to enable a direct conversion. If both Roll Pallets and Pallets are being used then this value should be the correct conversion factor applicable to the DU Types being used.

It also contains a flag to indicate whether quantities of each type can be decimal values. This determines whether the quantity values throughout the system in following forms will be allowed to be a decimal value: Orders, Trip Summary, Lane Based Order Entry, Order Entry Target, Order Templates, Order Tracking, Debrief by Invoice, Trip Manipulation and Trip Debrief.

The DU category can be specified to denote the type of despatch unit for planning purposes.

A DU category of "PALLET" indicates that it is a pallet that would normally be transported by own fleet.

A DU category of "PARCEL" indicates that it is a parcel that would normally be transported by a parcel carrier service by own fleet or by an external "PARCEL" carrier.

Note that a DU type will have a DU category of "PALLET" by default unless stated otherwise.

The DU category of an order will be set to "PARCEL" based on the presence of a DU type having a DU category of "PARCEL".

The DU category will then be used to decide which set of routes (fixed for "PALLET" or carrier for "PARCEL") to check for the derivation of the order time windows when the orders are created via the XML and CSV files.

DU Types may also be imported through **Imports**:

- **DU_TYPE**

Note that some "PARCEL" carriers will be able to take "PALLET" items should they be setup to do so in the "Carrier Rules" screen for the DU types.

To enter a new DU type click **New**:

Volume	Vol Collapsed	Max KG	RPE	Priority	AVG Wt	Decimals	No Re-Calc	Owned Pack
0.05	.0500	1.0	1.0000			<input checked="" type="checkbox"/>	<input checked="" type="checkbox"/>	<input checked="" type="checkbox"/>

Key in the required information and click **Save** or **Cancel** to return to the main form.



DU Types may be assigned an average weight and dimensions. When a particular Despatch Unit is added to an order through the various mechanisms of order creation (Portal, order entry, EDI etc) the dimensions added for the dispatch unit will be pulled through to the order where required.

Where applicable, users are able to identify those packages that belong to the transport organization itself, rather than being owned by an external customer. All customer packaging will be further defined in the customer Despatch unit screen. This will allow the system to distinguish the transport companies own and customer provided packaging. The transport companies packaging will not be assigned to a customer.

You can use the search buttons to find the new DU Type and the edit to make any changes.

1.14 Standardised DU's

This allows you to cross-reference customer DUs with standard DUs.

This maps customer and own packaging types to a list of standard DU types. The list of standard DU types are used to define package types in the contract.

You can enter the customer DU and the standard DU.

1.15 RPEs

This allows you to maintain RPE combinations.

You can enter:

- DU Type - a lookup is provided.
- Product Type - a lookup is provided.
- Loc Type - a lookup is provided.
- Volume
- Vol Collapsed
- Max KG
- RPE
- Priority

1.16 RPE Cust

This allows you to maintain RPE combinations for customers.

You can enter:

- DU Type - a lookup is provided.
- Product Type - a lookup is provided.
- Customer
- From Loc - a lookup is provided.
- To Loc - a lookup is provided.
- Volume
- Vol Collapsed
- Max KG
- RPE
- Priority
- Dry Ice
- Gel Packs
- Weight
- Charge
- Charge Point



1.17 Load Rates


Configuration of the rates taken to load different DU types is provided in this section.

Typically, this is used to represent the particular dispatch units onto Trailers and also includes categories such as default start-up and close-down times.

Load Rates can be configured to fix time at locations where product is either loaded or unloaded; a fixed value can also be applied to the start up and close down of a trip as detailed below.

To create a new load rate, click **New**:






- Loading Rate - Enter the name for the Loading Rate,
- SU/CL Mins - any time to be applied at start up or close down
- Apply Fixed Mins at SU/CL - select whether or not the fixed minutes below is also applied at SU/CL stops on top of the fixed minutes above.
- Fixed Mins - define any fixed time to be applied at stops which can then be added to a value per despatch unit:
- Dflt Mins per Du
- Mins per Weight

Clicking **Save** and **Cancel** will return you to the main form.

You can also assign different DU types to a load rate with varying default mins for loading/unloading,

To do this, select the rate and then click **New** on the right-hand panel - the "Insert Load Rate Detail" will be shown.





Enter the DU Type (using the supplied look up) and rate in mins.

Click **Save** and the form is updated with the new entry. You can continue and enter another DU type or click **Cancel** to return to the main form.

1.18 Despatch Units

Despatch Units can be configured here. This can be used to track individual DUs such as when, say, pallets are tracked to prevent loss and maximise re-use.

1.19 Tractors

Tractor units can be configured on this screen. A registration number should be used as the Id to identify the trailer. The Trip Manipulation forms then use this information to provide a list of valid vehicles that can be assigned to a Trip. A Tractor can be assigned to a Carrier to ensure they are assigned to appropriate Trip.



In a similar way to Drivers, Tractors can be allocated to trips to enable more accurate control of resources. Any tractors set up in this form will be available to select from a list displayed from the Trip Manipulation form if the carrier applied to the trip is set to "Poplist". Tractors set to "Inactive" will not be selectable.

To create a new tractor click **New** in the tractors box of the form:

Enter the "Tractor Id", "Tractor Type" and a "Description" - these are all free text fields.

Click **Save** and the system will confirm the tractor has been saved, but needs to be linked to a carrier. Click **OK**.

You can assign the carrier from this screen. Place the cursor in the Carrier data block and enter CTRL-L to see a list of Carriers.



Select the carrier and press **OK**. This will be the carrier id of the depot where the tractor is based.

The tractor will now be available to assign to trips when using the carrier the tractor has been allocated to.

You can also assign or change the carrier after a tractor is created. Using the search buttons find the tractor you have just created and click on it.

From the allocation to resources box click **New**:

Allocate a carrier id to the tractor. This will be the carrier id of the depot where the tractor is based. You can use a lookup of carriers here.

Click **Save**. The tractor is now allocated to the carrier id. The tractor will now be available to assign to trips when using the carrier the tractor has been allocated to.

If the tractor id is no longer required you are able to make it inactive. This follows the same process as making a trailer id and driver id inactive.

Using the search buttons find the tractor you want to make inactive and click **Edit** from the Allocation to Resources box.

Click in the "Inactive" check box, so a tick appears.

Click **Save**. The tractor id is now inactive.

You can also import tractors through [Imports](#):

- TRACTOR

1.20 Vessels

This allows you to maintain carrier vessels.

You can enter the vessel ID, Name and Carrier ID.



1.21 Resource Availability

This allows you to maintain resource availability per hour.

 **Note:** When using vehicles, this is superseded by the use of shifts and the resource availability calendar.

You can find resource availability by Depot, Date, Resource Type or ID.

The screen will display the resource type and ID for that criteria. The resource availability is colour coded green (available) and red (unavailable).


You can then maintain whether that resource is available in that hour of that day by clicking on the cell - the colour will flip between green (available) and red (unavailable).

You can switch to previous and next days using the buttons provided.

You can view a day, tear and month summary using the **Summary** button provided.

1.22 Carrier Routing

The gazetteer data can be imported for each carrier for the latest version to be applied:



Label Format	Version	Country Code	Country Name	From Postcode	To Postcode	Town	Sortation Hub
DHL_Express	84	GB	United Kingdom	AB10	AB10	ABERDEEN	ABZ
DHL_Express	84	GB	United Kingdom	AB10	AB10	BRIDGE OF DEE	ABZ
DHL_Express	84	GB	United Kingdom	AB11	AB11	ABERDEEN	ABZ
DHL_Express	84	GB	United Kingdom	AB11	AB11	TORRY	ABZ
DHL_Express	84	GB	United Kingdom	AB12	AB12	PORTLETHEN	ABZ
DHL_Express	84	GB	United Kingdom	AB12	AB12	MARYCULTER	ABZ
DHL_Express	84	GB	United Kingdom	AB12	AB12	WEST TULLOS INDUS	ABZ
DHL_Express	84	GB	United Kingdom	AB12	AB12	ALTENS	ABZ
DHL_Express	84	GB	United Kingdom	AB12	AB12	BRIDGE OF DEE	ABZ
DHL_Express	84	GB	United Kingdom	AB12	AB12	BADENTOY INDUSTRI	ABZ
DHL_Express	84	GB	United Kingdom	AB12	AB12	ABERDEEN	ABZ
DHL_Express	84	GB	United Kingdom	AB12	AB12	COVE BAY	ABZ
DHL_Express	84	GB	United Kingdom	AB12	AB12	COVE	ABZ
DHL_Express	84	GB	United Kingdom	AB12	AB12	ARDOE	ABZ
DHL_Express	84	GB	United Kingdom	AB12	AB12	BLAIRS	ABZ

The carrier routing data will be used for the production of the carrier labels and this data should be used to specify the carrier rules for ensuring that the orders are scheduled correctly. Note that this data is not used in the scheduling engine or the derivation of the order time windows.

1.23 Carrier Routing UKMail

This tab shows carrier routing specific to UKMail.



1.24 Carrier Formats

This allows you to maintain carrier formats (manifest and Zebra labels) used by carriers.

Different formats can be setup for each carrier:

Type	Format	Print Total on Label	Current Version	Activation Date	Delete Version
Label	DHLStandard1				
Label	DHL_Express2	Y	84	05-MAR-2016 10:25:26	
Label	Movianto	Y	84	11-DEC-2014 08:25:34	
Label	DHL_Express	Y	84	03-MAY-2013 13:29:00	
Label	Parcelforce	Y			
Label	Polarspeed	Y	25	29-JUL-2016 17:04:38	
Label	DHL_Penguin1	Y			
Label	Standard1	Y			
Label	Yodel	Y	130	27-FEB-2015 10:43:57	
Manifest	DHL Express				
Manifest	Yodel				
Manifest	Movianto				
Manifest	Standard1				
Manifest	Standard2				

The current version of the gazetteer data can be stored for the label format.

1.25 Carrier Tracking

The tracking references can be applied by customer by depot.

The tracking references can be updated with a range of values for the carriers:

Ref Type	Tracking Level	Prefix	Check Digit Function	Check Digit	Start	End	Next
CHE_DU	Shipment			6	1	999999999	219806
CITY_DU	Shipment				1	999999999	1
DHLCHER	Shipment	DHLCHER		6	1	999999	1287
DHLTD_AWB_Sh	Shipment		Standard1 (MOD7)	4	469100000	469144999	469128531
DHLTD_LPN_DU	DU	JD0002263200	Standard1 (MOD7)	3	1	500000	289411
DHL_AWB_NEW	Shipment		Standard1 (MOD7)	5	990597000	990641999	990597000
GLAV_Shpt	Shipment	GLAV	Standard1 (MOD7)	4	100000	499999	159002
PAR1_Shpt	Shipment	YD	Parcelforce	6	50000	149999	67223
PAR3_OLD	Shipment	YE	Parcelforce	6	400000	499999	400000
PAR3_Shpt	Shipment	GW	Parcelforce	7	10000	109999	81800
PEN_DU	DU	PEN	Standard1 (MOD7)	5	1	999999999	21467
POL_DU	DU	DHL	Standard1 (MOD7)	5	100000000	200000000	10476541
POL_Shpt	Shipment	CON	Standard1 (MOD7)	0	100000000	200000000	10384507
SAM_DU	DU	SAME		2	1	999999999	9921
TBD_Shpt	Shipment			5	1	999999999	5612



1.26 Carrier Config

The carrier can be configured to have a label format and a manifest format:

Location	Customer	Schedule Number	Account Number	Contract Number	Shipment Tracking Ref	Unit Tracking Ref
DHLLUTT	DEX		186227040		DHLTD_AWB_Sh	DHLTD_LPN_DU
DHLLUTT	HAE		186227079		DHLTD_AWB_Sh	DHLTD_LPN_DU
DHLLUTT	GLM		186226823		DHLTD_AWB_Sh	DHLTD_LPN_DU
DHLLUTT	FER		186461437		DHLTD_AWB_Sh	DHLTD_LPN_DU
DHLLUTT	SOR		186470772		DHLTD_AWB_Sh	DHLTD_LPN_DU
DHLLUTT	SET		185411637		DHLTD_AWB_Sh	DHLTD_LPN_DU
DHLCHER3	SER		186227095		DHLTD_AWB_Sh	DHLTD_LPN_DU
DHLCHER3	ACV		186226500		DHLTD_AWB_Sh	DHLTD_LPN_DU
DHLCHER3	ALG		185948672		DHLTD_AWB_Sh	DHLTD_LPN_DU
DHLCHER3	NOR		186144103		DHLTD_AWB_Sh	DHLTD_LPN_DU
DHLCHER3	CPK		186692417		DHLTD_AWB_Sh	DHLTD_LPN_DU
DHLCHER1	ARR		186226034		DHLTD_AWB_Sh	DHLTD_LPN_DU

The physical manifest can also be requested to be printed automatically when the trip is despatched.

1.27 Vehicles

This allows you to maintain fixed vehicles (e.g. vans).

Reg No	Fleet	Vehicle Type	Carrier	Vin No	Exc	Epod	TomT...	T/Lift	B/Light	VOR
AV16FXF	51209	VAN	BRM		<input checked="" type="checkbox"/>					
AV16JZT	51210	VAN	NEW		<input type="checkbox"/>					
AV16SXN	51206	VAN	COA		<input type="checkbox"/>					
AV16VFG	51213	VAN	LBZ		<input type="checkbox"/>					
AY18RVX	56109	VAN	POM		<input type="checkbox"/>					
AY18RVZ	56114	VAN	SCO		<input type="checkbox"/>					
AY18RWE	56113	VAN	COA		<input type="checkbox"/>					
AY18RWF	56111	VAN	SWA		<input type="checkbox"/>					
AY18RWJ	56112	VAN	BAM		<input type="checkbox"/>					
AY18RWK	56110	VAN	EXE		<input type="checkbox"/>					
AY18RWL	56108	VAN	NEW		<input type="checkbox"/>					
AY18SRZ	56119	VAN	BRM		<input type="checkbox"/>					
AY18SSJ	56117	VAN	PRE		<input type="checkbox"/>					
AY18SSK	56116	VAN	BAM		<input type="checkbox"/>					
AY18SSO	56120	VAN	NEW		<input type="checkbox"/>					



Fixed vehicles consist of a tractor and trailer, linked together. The tractor and trailer will have the same ID. You will enter all details related to tractor and trailer in one screen.

The vehicles tab is used to set up vehicles that are to be assigned to trips. On entry to the tab you are presented with a list of vehicles that are already set up on the system. You can search on registration number, fleet, vehicle type and carrier. All fields have a list of values and pressing the **Refresh** button will bring back the data you are looking for.

To bring back all the data press the **Clear Search Criteria** button.

Five buttons are available at the foot of the screen:

- **Diary Exceptions**
- **New**
- **Edit**
- **Delete**
- **Close** - To exit the screen

1.27.1 New

To create a new vehicle press the **New** button. The following screen is shown:

Enter the data relevant to the vehicle. The vehicle type and carrier are selected from a drop down list. the Blue light, Tail Lift, Epod enabled, TomTom enabled and VOR fields will be a checkbox where checked indicates a positive value. Press the **Save** button to create the vehicle on the database. You will be returned to the main screen.

The compartments section controls creation and amendment of the compartments associated with the vehicle. The functionality for the compartments mirrors the functionality in the trailer types tab of the resources screen.

Creating records using the Vehicles tab page will also create the associated records in the Trailer ID with compartments, Tractor ID and Trailer to Tractor link.

Two buttons will be included in the footer of the screen:

- **Cancel** - Display a message asking the user to confirm that any updates made will be abandoned once confirmed rollback any changes and close the window.
- **Save** - Validate all changes and commit, if any field fails validation display an appropriate error message.



1.27.2 Edit

From this screen you can change the details of a vehicle by pressing the edit button. The following screen is displayed . All fields can be changed except for the registration number. The right hand side of the screen is informational data associated with the vehicle type and cannot be edited.

Vehicle Details

Reg No	AV16FXF
Fleet	51205
Vehicle Type	VAN
Vin No	
TomTom Enabled	<input type="checkbox"/> TomTomRef
Epod Enabled	<input type="checkbox"/> Tail Lift <input type="checkbox"/>
Blue Light	<input type="checkbox"/> VOR <input type="checkbox"/>
Narrative	Mercedes-Benz 316 CDi

Compartment	Max RPE	Position
A	3	1

Temp Combination	Temp Type	Compartment
AMBIENT	AMBIENT	A

Carrier Id

BRM	Inactive

Cancel Save Apply Close

If for any reason the vehicle is going to be unavailable for an unknown period of time you can check the VOR (Vehicle Off Road) tick box. Whilst this box is ticked the vehicle will not be able to be allocated to a trip. Press the **Save** button to commit the changes to the database or the **Cancel** button to abandon any changes you have made. You will then be returned to the main screen.

1.27.3 View

From here you can also view the details of the vehicle by pressing the **View** button. Whilst viewing you cannot change any data.

1.27.4 Delete

To remove a vehicle from the system press the **Delete** button. A confirmation message is displayed which allows you to either confirm or abandon the delete

1.27.5 Diary Exceptions

This screen has a **Diary Exceptions** button. This will display a popup window showing the activity the current vehicle has been allocated to, and so describes periods of unavailability. This activity can be either associated with a trip the vehicle has been allocated to, or manual records entered.



There are four buttons on the screen:

- **New** will allow a new activity to be entered for the current resource.
- **Edit** will allow editing of a record. When a resource is off the road, if it has been allocated to any subsequent activity a message will be displayed warning the user they may need to take action to remove resource from trips etc.
- **Delete** will display a confirmation message and once confirmed will remove the record
- **Close** will save any changes and return you to the main resource diary page.

To create a new record press the **New** button and enter the reason for the exception. Then enter the start and end date and time. The duration is calculated automatically. Press the **Save** button to commit the record to the database. To delete a record press the **Delete** button.

Note: Exceptions records created by planned trip activity related to the vehicle cannot be deleted.

Pressing the **Close** button will return you to the main screen.

1.27.6 Imports

You can also import vehicles and associated reference data through [Imports](#):

- VEHICLE

1.28 Carrier Hazard Qty

This tab is used to maintain the maximum quantities of hazardous classes that a carrier can carry.

1.29 Carrier Formats Mapping

The label format can be assigned to a routing format to obtain the gazetteer data:



