

WHS0010

Aptean Ltd
Copyright © 2011-2025.

Contents

1	WHS0010.....	1
1.1	System Parameters (WHS0010).....	1

1 WHS0010

1.1 System Parameters (WHS0010)

This screen maintains all the static formats that will be used to set up the warehouse. There are three tabs in all. This page will detail the setup required within the MAIN tab.

Warehouse specific information is maintained in this screen. The above set up is the generic set up for a basic warehouse. Please see information at the end of this user guide for more details on the client specific flags

Used to specify a number of parameters that will govern the way the system will operate and how various items of information will be formatted in this warehouse.

Note, again, the user must be logged in as the correct warehouse in order to make changes

Note:

- Auto Log Display determines whether the user wishes to see the allocation log once a set of orders has been allocated
- Pick Note and Pal Move Lines specifies the number of lines allowed on a printed pick or move note
- The Area, Aisle, Bay and Level lengths are used to determine the format of the location codes. I.E. A location code of AA-01-1A would have an aisle, bay and level length of 2 each (the area code is not included)
- Max. Rotation Length is the length of the system generated rotation number
- Loc Delimiter is the symbol used to separate the aisle, bay and level within the location code (for our example, the delimiter would be ?-?)
- The Rotation Type is how the system generates the rotation number, or whether it is to be manually entered by the user.
- Reduce Stk At will determine when stock is downdated during the order cycle. Note, this is extremely important, if you choose ?Pick Confirmation? Despatch will not be feasible .



1.1.1 GOODS IN TAB

The Goods In tab of the System Parameters screen specifies what functionality during goods receipt you wish to use.

System Parameters Maintenance
Owner: ROB Warehouse: NPT 10-JUN-2025 WHS0010 v4.19

Main Goods In Default Locations

Goods Receipt

Auto Putaway Flag: ☒ Yes ☐ No

Opposite Aisle Param: 999

Next Aisle Param: 999

GRN Consolidation: None

GRN Check Sheet: ☒ Yes ☐ No

Bonded Units Caged: ☒ Yes ☐ No

Hold Stk until Putaway: ☒ Yes ☐ No

Alloc at Pre-Advice: ☒ Yes ☐ No

Number Of Bays: 10

Integrated WMS: ☒ Yes ☐ No

Integrated Bay Diary: ☒ Yes ☐ No

Integrated Container Yard: ☒ Yes ☐ No

Max Warehouse Bay Bookings: 4

Max Refrigerated Yard Bookings: 2

Max Dry Yard Bookings: 2

Suggested Slot Window (Hours): 4

Inter-Warehouse Transfer

Suggest Locations: ☒ Yes ☐ No

Putaway Algorithm: Putaway Algorithm K

Set Cust Pallet to Old System Pallet: ☒ Yes ☐ No

Note:

- The Auto Putaway flag must only be set to ?Y? if you wish the system to dictate where stock is located during the goods receipt process
- The Opposite and Next Aisle Param fields are to determine how many locations you wish the system to search before moving to the next, or opposite aisle during Auto Putaway
- The Hold Stk until Putaway flag should always be set to ?Y? If this is not set, stock received on a goods receipt could be ordered before it has been physically located within the warehouse

1.1.2 DEFAULT LOCATIONS TAB

The Default Locations tab is used to determine which locations are to be used during certain automatic processes throughout the system.

Note, this screen cannot be set up until the location codes have been created. The user normally saves the first two tabs of System Parameters, then returns to complete this tab once the necessary locations have been created



System Parameters Maintenance

Owner: ROB Warehouse: NFI 10-JUN-2025 WHS0010 v4.19

Main Goods In Default Locations

ID Station:		Unbonded Putaway Locations:	01031
Reject Spur at ID Station:			TBU07
Q/A:	GI01A		
Turntable:			
Input Spur to Conveyor:		Bonded Putaway Locations:	
Default Marshalling Location:	MA011		
Default Despatch Bay Location:			
Pre-advise Virtual Location:	FL001		
Quarantine in Marshall:			
Auto Bulk Reject:			
Default Ship Pallet Build Locn:	MAR22		
Default Damages:	DM011		
Default Returns:	40101		
Problem Resolution:	20805		
Kit Assembly Location:	30101		
Default Cons Good Ret:			
Default Cons Bad Ret:			

Note:

- Only the Default Marshalling Location is used within generic basic warehouse set-up. Any other locations required will be determined by the client specific processes
- Note, failure to enter a marshalling location here will mean that it will be required to be manually entered for each allocation run.

