

Initial Installation

Aptean Ltd
Copyright © 2011-2025.

Contents

1 Initial Installation.....1

1 Initial Installation

I have created the following Projects folder:

```
P:\Calidus MCS\Support\RDC Connections
```

In here I have created a remote desktop connection for DOM-TST to connect to the shared-webapp machine (172.183.45.80). NOTE: May need following to access:

```
ROUTE -P ADD 172.183.0.0 MASK 255.255.0.0 10.43.0.93
```

I have connected onto the machine using the mcsadmin user.

I created the following folder structure on this machine:

```
C:\Program Files (x86)\OBSLogistics.mcs\MCS_domtst
```

I installed the programs from RBC test on the shared OBS server into this folder.

I modified web.config to point to this folder where required, and point to domttst database.

I created this as a website MCS_domtst on the machine in IIS.

- http
- Port 41080
- Application pool MCS_domtst.
- App Pool Advanced settings: Enable 32bit Applications: True

Enabled ASP.NET state services:

```
Settings/Services, ASP.NET State Service, right-click, set running.
```

Added TNS names for domttst and domtprd to C:\app\Administrator\product\11.2.0\client_1\network\admin\tnsnames.ora

Currently set up on <http://172.183.45.80:41080/>

- URLs required e.g. domtst.calidus-mcs.com or domtst_mcs.calidus.com.
- HTTPS?

Logged on successfully as MCS_ADMIN.

